Real time PCR





Classic polymerase chain reaction

Traditional End-Point PCR



- Low sensitivity
- Poor precision
- Results are not expressed as numbers
- Ethidium bromide staining is not quantitative
- •Post-PCR processing required
- •Narrow dynamic range (<2 logs)

Traditional End-Point PCR

has a narrow dynamic range (<2 logs) → SEMI-QUANTITATIVE



Background of end point PCR

Traditional End-Point PCR



End-point PCR:

- → ideal to give qualitative information (for example amplification of a mutation using specific primers)
- ightarrow Only limited quantitative information possible

Optimizing quantitive information from classic PCR

Adjust ideal number of cycles



Get better quantitative information from classic PCR:

- Optimize PCR conditions:
 - A. Test for ideal end-point of PCR (example 25)
 - B. Optimize the amount of original template used for PCR

Time Waste of primary material Costs Variability

Real-time PCR

Follow PCR product amplification in real-time (RT-PCR)

Obtaining QUANTITATIVE information from PCR



Follow the amplification of PCR amplicons in "REAL-TIME" = REAL TIME PCR

Real-time PCR

Eliminate use of gel electrophoresis
Increase reproducibility
Enable use of internal controls/standards
Reduce turnaround time
Increase throughput
Reduce sample amount usage
Results expressed as numbers





Real-Time PCR Chemistries

Strategies to follow PCR product generation

SYBR[®] Green I dye



Binds double stranded DNA

Fluorogenic 5' Nuclease Assay



Uses a TaqMan[®] probe

1. SYBR® Green I Dye Assay Chemistry

Classic PCR setup with addition of SYBR Green: SYBR Green is a green fluorescent cyanine dye that has high affinity for double-stranded DNA. The mode of binding is believed to be a combination of DNA intercalation and external binding. When bound, SYBR absorbs at a wavelength around 497 nm and emits fluorescence around 520 nm.





DNA synthesis Detection of emission of fluorescence

1. Dye in solution emits low fluorescence 2. Emission of the fluorescence by binding

Fluorescence emmission is increasing with increasing of PCR cycles



Every PCR cycle: Exitation of SYBR green (497nm) + measurment of emission from SYBR green (520nm)

Fig. 1.2. Representation of Optical Detection System layout.

AMPLIFICATION BLOT



Quantitative information

METLTING CURVE ANALYSIS

The temperature-dependent dissociation between two DNA-strands can be measured using a DNA-intercalating fluorophore such as SYBR green, or fluorophore-labelled DNA probes. In the case of SYBR green (which fluoresces 1000-fold more intensely while intercalated in the minor groove of two strands of DNA), the dissociation of the DNA during heating is measurable **by the large reduction in fluorescence that results.**

The temperature at which 50% of DNA is denatured is known as the melting temperature.



Melting curve is determined after the last cycle of PCR:

- → PCR machine heats uo PCR products from 0°C to 100°C
- → Dissociation of DNA filaments is measured
- → IF PCR HAS AMPLIFIED SPECIFICALLY AMPLIFIED A SPECIFIC REGION ALL DNA MOLECULES WILL MELT AT A SPECIFIC TEMPERATURE → melting temperature is determined by DNA sequence!!!
- \rightarrow IF YOU RUN PCR PRODUCT ON AGAROSE GEL, ONLY ONE BAND WILL BE VISIBLE

METLTING CURVE ANALYSIS

Melting curve is determined after the last cycle of PCR:

- → PCR machine heats uo PCR products from 0°C to 100°C
- → Dissociation of DNA filaments is measured
- → IF PCR HAS AMPLIFIED MULTIPLE FRAGMENTS IN A NON_SPECIFIC MANNER THE MELTING CURVE ANALYSIS WILL IDETIFY MORE THEN ONE PEAK (PCR primers are not sepcific!!)
- → Example: IF YOU RUN PCR PRODUCT ON AGAROSE GEL, FIVE BANDS WILL BE VISIBLE



METLTING CURVE ANALYSIS GIVE QUALITATIVE INFORMATION OF THE REAL-TIME PCR REACTION (without necessarily requiring an agarose gel run)

Real-Time PCR Chemistries

Strategies to follow PCR product generation

SYBR[®] Green I dye



Binds double stranded DNA

Fluorogenic 5' Nuclease Assay



Uses a TaqMan[®] probe

Classic PCR setup with addition of amplicon-specific, modified ssDNA oligonucleotide





Fluorescence Resonance Energy Transfer

Taqman probe:

- Oligonucleotide
- PCR amplicon site specific
- Hybridizes with one strand of the PCR product
- Carries a fluorophor (R)
- Carries a Quencher that absorbes light emited from fluorophor ="FRET"

Important: FRET only works when Q is in close proximity to R



*FRET= Fluorescence Resonance Energy Transfer



Loss of FRET: light from R is not cheched and can be detected in "real-time" during PCR

Fluoresence increases with every cycle of PCR until reaching saturation in PCR plateau phase



ADVANTAGE:

HIGHLY SPECIFIC DETECTION OF AMPLIFIED DNA REGIONS:

- **1. Sequence specific PCR primers for PCR**
- 2. Amplicon specific DNA probe enables selective detection of region of interest!!!



2 parallel PCR reacations shown in blot: BLUE: PCR with template RED: PCR without template (negative control)

Rn: reporter signal obtained from detector







WITH EVERY CYCLE OF PCR, THE AMOUNT OF AMPLIFIED DNA DOUBLES

 $Y = N (1+E)^n$

- Y = resa di amplificazione/amount amplifid
- N = numero di molecole di DNA di partenza (number of starting DNA molecules)
- **E** = efficienza di reazione (efficieny of reaction)
- n = numero di cicli di amplificazione (number of PCR cycles)

The amount of initial DNA is reverse proportional to the number of cicles required to overcome the threshold (arrive at Ct)



Basics for the analysis of real-time PCR data: C_t and Δ C_t

WITH EVERY CYCLE OF PCR, THE AMOUNT OF AMPLIFIED DNA DOUBLES



Analysis of real-time PCR data: C_t and ΔC_t



Analysis of real-time PCR data: C_t and ΔC_t



Provides absolute measurement of starting copy *number*

-Requires standards of known quantity (Mol or ng)
-e.g. Forensic science: Is there DNA and how much DNA (copy number) is there for forensics purposes
- e.g. Diagnostics: Virus titer in blood: is there virus DNA and how much is there?

Basics for the analysis of real-time PCR data: C_t and ΔC_t



C_ts derived from real-time PCR using and increased copy number of target site: PCR TARGET REGION MUST BE AVAILABLE AT (for example cloned into a plasmid) **DIFFERENT DILLUTIONS ARE USED FOR PCR TO GENERATE A STANDARD CURVE**

ABSOLUTE QUANTITATION

Biological samples with unknown copynumber of PCR target site

Basics for the analysis of real-time PCR data: C_t and ΔC_t



Basics for the analysis of real-time PCR data: C_t and ΔC_t



RELATIVE QUANTITATION

Provides accurate discrimination between relative amounts of starting material

-e.g. Comparing expression levels of wildtype vs. mutated alleles

-e.g. Comparing expression levels of a gene across different tissues or between different biological conditions

-e.g. Validating array results

Basics for the analysis of real-time PCR data: relative quantitation

RELATIVE QUANTITATION



Basics for the analysis of real-time PCR data: relative quantitation



Basics for the analysis of real-time PCR data: C_t and ΔC_t and $\Delta \Delta C_t$



What is Real-Time PCR used for?

Real-Time PCR has become a cornerstone of molecular biology:

Gene expression analysis

- Cancer research
- Drug research

Disease diagnosis and management

- Viral quantification
- Food testing
 - Percent GMO food
- Animal and plant breeding
 - Gene copy number

For all applications that require the quantification of RNA/DNA sequences